
DoSA-3D User Manual

Solenoid Example



2022-06-25 zgitae@gmail.com

DoSA Structure


PC Requirement

> CPU: 4 Core and above

> RAM: 16GB and above



Program Structure



Toolbar

1. Operations

✓ New : Create a new design

✓ Open : Open previous design

✓ Save : Save the design

✓ SaveAs : Save in different name

✓ Shape: Check the 3D Shape



2. Design

✓ Coil : Add a coil and specification design

✓ Magnet : Add a magnet and determine specifications

✓ Steel : Add a steel and determine specifications



3. Virtual Test


✓ Force : Magnetic force estimation



Work process

Product Design


Virtual Test



Analysis Model

Analysis Model

1. Model Shape



2. Product Specifications

A. Coil Turns

• Coil Turns: 1040 turns

• Coil Resistance: 15.2 Ohm

B. Power

• Voltage: 14.5V

(Example Files : DoSA-3D Install Directory > Samples > Solenoid)



New design

1. Toolbar > Click New Button

2. Design Name: "Solenoid"


3. Shape File (STEP): Select Solenoid.step (provided with this tutorial document)



[Cautions for the Shape Model]

DoSA-3D still has the following functional limitations.


- A. Shape constraint
 - Coil central axis must coincide with Y axis.
 - The current is always applied in cylindrical form. (Polygon coils can cause some differences)
- B. Limited number of parts
 - Actions only support one part.
 - Only one coil is supported.
- C. Drawing Guide
 - https://solenoid.or.kr/data/Drawing Guide ENG.pdf






New design

- 4. Check the solenoid shape in Gmsh.
- 5. Exit the Gmsh.
- 6. Check the part names.
- 7. Click the OK button if there are no problem with the shape and part names.








New design


8. Check the design creation.




Parts Design

Add a Coil

- 1. Toolbar > Click Coil button
- 2. Select "Coil" in the list box.
- 3. Click the OK button.







Coil design

1. Input Coil specifications

✓ Inner Diameter: 9.6

✓ Outer Diameter: 21.6


✓ Coil Height : 16

✓ Copper Diameter: 0.27

2. Calculate the coil specification


✓ Click "Coil Design" button

3. Check the coil specification



4	Common Fields	
_	Node Name	Coil
4	Specification Fields	
_	Part Material	Copper
	Curent Direction	IN
	Moving Parts	FIXED
Δ	Calculated Fields	
	Coil Turns	1040
	Coil Resistance [Ω]	15, 20945
	Coil Layers	20
	Turns of One Layer	52
■ Design Fields (optional)		
	Coil Wire Grade	Enameled_IEC_Grade_2
	Con mic arade	CHameleu_ICC_Grade_Z
	Inner Diameter [mm]	9,6
	Inner Diameter [mm]	9,6
	Inner Diameter [mm] Outer Diameter [mm]	9,6 21,6 16
	Inner Diameter [mm] Outer Diameter [mm] Coil Height [mm]	9,6 21,6 16
	Inner Diameter [mm] Outer Diameter [mm] Coil Height [mm] Copper Diameter [mm]	9,6 21,6 16 0,27
	Inner Diameter [mm] Outer Diameter [mm] Coil Height [mm] Copper Diameter [mm] Wire Diameter [mm]	9,6 21,6 16 0,27 0,31072
	Inner Diameter [mm] Outer Diameter [mm] Coil Height [mm] Copper Diameter [mm] Wire Diameter [mm] Coil Temperature [*C]	9,6 21,6 16 0,27 0,31072 20

1







3

Add an Armature

- 1. Toolbar > Click Steel button
- 2. Select "Armature" in the list box.
- 3. Click the OK button.







Armature setting


1. Armature setting


✓ Part Material : SUS_430

✓ Moving Parts: MOVING

Select the magnetic force calculation part


[BH 곡선]






Add a core

- 1. Toolbar > Click Steel button
- 2. Select "Core" in the list box.
- 3. Click the OK button.








Core setting


1. Core settings

✓ Part Material : SUS_430






1




Add a case

- 1. Toolbar > Click Steel button
- 2. Select "Case" in the list box.
- 3. Click the OK button.










Case setting


1. Case Settings

✓ Part Material : SUS_430





1



Virtual Test

Test of the magnetic force

1. Toolbar > Click Force Button

2. Force Test Name: "Force"

3. Click OK Button


4. Setting of magnetic force test


✓ Voltage: 14.5


✓ B Rotation Angle : 45 ✓ Mesh Size Percent : 7

5. Click "Force Test" Button












Run the virtual test


- 6. Check the progress of magnetic force analysis.
- 7. Check the magnetic density and force. (The solving time is depend on you system specification)







Results of the virtual test

- 8. Check the full magnetic density.
- 9. Check the section magnetic density.











Tips

Open Design

- 1. Toolbar > Click Open Button
- 2. Double click the design directory.
- 3. Double click the design file.









Thank You

Email: zgitae@gmail.com

Homepage: http://openactuator.org