


DoSA-Open_3D User Manual

Example of Solenoid




2020-12-02

GiTae Kweon (zgitae@gmail.com)


DoSA Structure

PC Requirement

- CPU : 4 Core and above
- RAM : 16GB and above



Program Structure



Toolbar


1. Operations

- ✓ New : Create a new design
- ✓ Open : Open previous design
- ✓ Save : Save the design
- ✓ SaveAs : Save in different name
- ✓ Shape : Check the 3D Shape



2. Design

- ✓ Coil : Add a coil and specification design
- ✓ Magnet : Add a magnet and determine specifications
- ✓ Steel : Add a steel and determine specifications



3. Experiment



- ✓ Force : Magnetic force estimation for driving part



Analysis Model

Analysis Model

1. Model Shape



2. Product Specifications

A. Coil Turns

- Coil Turns : 1040 turns
- Coil Resistance : 15.2 Ohm

B. Power

- Voltage : 14.5V

(Example Files : DoSA-Open_3D Install Directory > Samples > Solenoid)

New design

1. Toolbar > Click New Button



2. Design Name : "Solenoid"

3. Shape File (STEP) : Select Solenoid.step (Example Files : DoSA Install Directory > Samples > Solenoid)

[Precautions for the Shape Model]


DoSA-Open_3D still has the following functional limitations.

ㄱ. Limitation of Coil Shape

- Coil center axis should be Y axis direction.
- The current is applied like a cylindrical coil.
(Square coils can cause some differences)


ㄴ. Moving Part

- The moving part still supports only one component..




New design

4. Check the solenoid shape in Gmsh.
5. Exit the Gmsh.
6. Check the part names.
7. Click the OK button if there are no problem with the shape and part names.



New design



8. Check the design creation.



Parts Design

Add Coil

1. Toolbar > Click Coil button
2. Select "Coil" in the list box.
3. Click the OK button.



Coil design

1. Input Coil specifications

- ✓ Part Material : Copper
- ✓ Current Direction : IN (Inner Direction)
- ✓ Moving Parts : FIXED (Fixed Part)
- ✓ Coil Wire Grade : Enameled_IEC_Grade_2
- ✓ Inner Diameter : 9.6 mm
- ✓ Outer Diameter : 21.6 mm
- ✓ Coil Height : 16 mm
- ✓ Copper Diameter : 0.27 mm
- ✓ Horizontal Coefficient : 0.9 (Enameled Type)
- ✓ Vertical Coefficient : 0.98 (Enameled Type)
- ✓ Resistance Coefficient : 1 (Enameled Type)

2. Calculate the coil specification

- ✓ Click "Coil Design" button

2



Coil Design

1

Common Fields	
Node Name	Coil
Specification Fields	
Part Material	Copper
Current Direction	IN
Moving Parts	FIXED
Calculated Fields	
Coil Turns	1040
Coil Resistance [Ω]	15,20945
Coil Layers	20
Turns of One Layer	52
Design Fields (optional)	
Coil Wire Grade	Enameled_IEC_Grade_2
Inner Diameter [mm]	9,6
Outer Diameter [mm]	21,6
Coil Height [mm]	16
Copper Diameter [mm]	0,27
Wire Diameter [mm]	0,31072
Coil Temperature [$^{\circ}\text{C}$]	20
Horizontal Coefficient	0,9
Vertical Coefficient	0,98
Resistance Coefficient	1

Add Armature

1. Toolbar > Click Steel button
2. Select "Armature" in the list box.
3. Click the OK button.




Armature setting

1. Armature setting

- ✓ Part Material : SUS_430
- ✓ Moving Parts : Moving (Moving Part)

[BH 곡선]





1

Common Fields	
Node Name	Armature
Specification Fields	
Part Material	SUS_430
Moving Parts	MOVING

Add core

1. Toolbar > Click Steel button
2. Select "Core" in the list box.
3. Click the OK button.




Core setting

1. Core settings

- ✓ Part Material : SUS_430
- ✓ Moving Parts : FIXED (Fixed Component)

[BH 곡선]





1

Common Fields	
Node Name	Core
Specification Fields	
Part Material	SUS_430
Moving Parts	FIXED

Add case

1. Toolbar > Click Steel button
2. Select "Case" in the list box.
3. Click the OK button.




Case setting

1. Case Settings

- ✓ Part Material : SUS_430
- ✓ Moving Parts : FIXED (Fixed Component)

[BH 곡선]




1

Common Fields	
Node Name	Case
Specification Fields	
Part Material	SUS_430
Moving Parts	FIXED


Virtual Experiments

Virtual Experiment of magnetic force

1. Toolbar > Click Force Button
2. Force Experiment Name : "Force"
3. Click OK Button
4. Setting of magnetic force experiment
 - ✓ Voltage : 14.5 V
5. Setting of analysis condition
 - ✓ Mesh Size Percent : 5 %
 - ✓ Actuator Type : Solenoid
6. Click "Force Test" Button




▼ Common Fields	
Node Name	Force
▼ Input Fields	
Voltage [V]	14.5
Max. Current [A]	0,95335
▼ Initial Position Fields	
Y Movement [mm]	0
X Movement [mm]	0
Z Movement [mm]	0
▼ Condition Fields	
Mesh Size [%]	5
Actuator Type	Solenoid




Run the virtual experiment

7. Click the Run button after checking the shape.



Results of the virtual experiment

8. Check the analysis results after solving. (The solving time is depend on you system specification)
9. **Quit the Gmsh.**
10. If you want to see the analysis progress, click the status bar of the Gmsh.
11. Check a magnetic force of the solenoid.



Thank You